

© 1989–2009 Paradigm B.V. and/or its affiliates and subsidiaries. All rights reserved.

The information in this document is subject to change without notice and should not be construed as a commitment by Paradigm B.V. and/or its affiliates or subsidiaries (collectively, "Paradigm"). Paradigm assumes no responsibility for any errors that may appear in this document.

The Copyright Act of the United States, Title 17 of the United States Code, Section 501 prohibits the reproduction or transmission of Paradigm's copyrighted material in any form or by any means, electronic or mechanical, including photocopying and recording, or by any information storage and retrieval system without permission in writing from Paradigm. Violators of this statute will be subject to civil and possible criminal liability. The infringing activity will be enjoined and the infringing articles will be impounded. Violators will be personally liable for Paradigm's actual damages and any additional profits of the infringer, or statutory damages in the amount of up to \$150,000 per infringement. Paradigm will also seek all costs and attorney fees. In addition, any person who infringes this copyright willfully and for the purpose of commercial advantage or private financial gain, or by the reproduction or distribution of one or more copies of a copyrighted work with a total retail value of over \$1,000 shall be punished under the criminal laws of the United States of America, including fines and possible imprisonment.

The following are trademarks or registered trademarks of Paradigm B.V. and/or its affiliates or subsidiaries (collectively, "Paradigm") in the United States or in other countries: Paradigm, Paradigm logo, Alea, Coherence Cube, Director, DirectorGeo, EarthStudy 360, Echos, Epos, FastVel, FracMV, GeoDepth, Geolog, GeoScene, GeoSec, GeoSteer, GOCAD, Interpret, Jacta, Kine3D, OpenGeo, OpsLink, Probe, Pump-It, Rock & Fluid Canvas, SeisEarth, SeisFacies, SeisX, SKUA, SolidGeo, StratEarth, Stratimagic, Sysdrill, UVT Transform, Vanguard, VoxelGeo, and/or other Paradigm products referenced herein. All other company or product names are the trademarks or registered trademarks of their respective holders.

Alea and Jacta software under license from TOTAL. All rights reserved.

Some components or processes may be licensed under one or more of U.S. Patent Numbers 5,570,106; 5,615,171; 6,765,570; and 6,690,820.

Some components or processes are patented by Paradigm and/or one or more of its affiliates under U.S. Patent Numbers 5,563,949; 5,629,904; 5,838,564; 6,092,026; 6,430,508; 6,819,628; 6,859,734; 6,873,913; 7,095,677; 7,123,258; 7,295,929; and 7,295,930. In addition, there may be patent protection in other foreign jurisdictions for these and other Paradigm products.

All rights not expressly granted are reserved.

Before You Begin

About This Guide

This guide explains how to install Paradigm™ GOCAD® 2009.1, Basic Developer Kit 2009.1, and Workflow Developer Kit 2009.1 in both Linux and Microsoft Windows environments. To complete the installations described in this guide, you need some familiarity with the operating system on which you are installing the software.

GOCAD 2009.1 includes the following products:

Discipline	Product
Geosciences	Base Module Structural Framework Builder
Seismic Interpretation	Interpretation Modeling Seismic Attribute Analysis Rock Volume Uncertainty Assessment (Alea®) ¹
Velocity Modeling	Velocity Modeling and Time Depth Conversion
Geologic Interpretation	Stratigraphic Modeling and Fault Analysis Well Correlation and Stratigraphic Analysis Advanced Structural Analysis (Kine3D-1) ² 2D Restoration (Kine3D-2) ² 3D Restoration (Kine3D-3) ²
Reservoir Modeling	3D Reservoir Grid Builder Reservoir Data Analysis Reservoir Properties Object Modeling Reservoir Risk Assessment (Jacta®) ¹ HP Reservoir Risk Assessment (Jacta Cluster) ¹ Finite Element Mesh Constructor

(Continued 1 of 2)

Discipline	Product
Reservoir Production	LGR and Upscaler Fracture Modeling (FracMV) ³ Production Data Loader Production Data Analysis Reservoir Simulation Interface (ECLIPSE, 3DSL) Production Risk Assessment 3DSL Connection Production Risk Assessment FrontSim Connection
Drilling Planner	Basic Well Planning Side Track and Collision Risk
System and Complements	Epos™ Link Remote Collaboration OpenSpirit Client
(Continued 2 of 2)	

1. Developed in cooperation with Total.
2. Developed in cooperation with Institut Français du Pétrole (IFP).
3. Developed in cooperation with Midland Valley.

The installation process installs the entire suite of modules, and a license server controls access according to the products that you purchase. This guide also includes information about how to install and configure the license server.

Note For information about compatibility with SKUA, StratEarth™, and other Paradigm products, see the *User Guide, Part I: Getting Started*.

Contents

	Before You Begin	iii
	About This Guide	iii
Chapter 1	Supported Operating Systems and Requirements	1-1
1.1	Common System Requirements	1-2
1.2	Specific Requirements for Supported Operating Systems.....	1-2
1.3	Additional Software Requirements.....	1-3
1.4	About Windows for x86 (32-Bit) and x64 (64-Bit) Systems	1-4
Chapter 2	Installing GOCAD 2009.1 and SKUA 2009.1	2-1
2.1	Installation Process	2-2
2.2	Downloading GOCAD, SKUA, and Related Products	2-2
2.3	Installing GOCAD 2009.1 and SKUA 2009.1	2-4
2.3.1	Installing GOCAD and SKUA on Linux	2-4
2.3.2	Installing GOCAD and SKUA on Windows	2-6
2.3.3	Configuring GOCAD and SKUA to Run from a Shared Location (Windows).....	2-7
2.4	Starting GOCAD 2009.1 or SKUA 2009.1	2-9
2.4.1	Starting GOCAD 2009.1 or SKUA 2009.1 on Linux	2-9
2.4.2	Starting GOCAD or SKUA on Windows	2-10
Chapter 3	Installing and Configuring License Server 11.6	3-1
3.1	About License Server	3-2
3.2	About Configuring Licenses for GOCAD 2009.1 and SKUA 2009.1	3-3
3.2.1	License Concepts	3-3
3.2.2	License Types	3-3
3.2.3	License File Components	3-4
3.3	Installing or Upgrading License Server 11.6 on Linux	3-6
3.3.1	Removing an Earlier Version of License Server.....	3-6

3.3.2	Installing a New License Server	3-7
3.3.3	Stopping License Server	3-8
3.4	Installing or Upgrading License Server 11.6 on Windows	3-9
3.4.1	Removing an Earlier Version of the License Server	3-9
3.4.2	Installing Dongle Device Drivers	3-10
3.4.3	Installing a New License Server	3-11
3.5	Setting Up the License Option File—Basic Developer Kit (Developer-Based)	3-16
3.6	Updating the License File	3-17
3.7	Frequently Asked Questions About License Server	3-18
3.7.1	How Do I Find the Host ID for My Computer?	3-18
3.7.2	How Do I Switch from One License Server to Another?	3-19
3.7.3	Why Did License Server Report an Invalid Host ID When I Disconnected My Notebook?	3-20
3.7.4	What Is the GOCADLMD_LICENSE_FILE Environment Variable?	3-20
Chapter 4	Installing Developer Kits	4-1
4.1	About Developer Products	4-2
4.2	Installation Process	4-2
4.3	About Qt	4-4
4.4	Installing Developer Kits	4-4
4.4.1	Installing a Developer Kit on Linux	4-5
4.4.2	Installing a Developer Kit on Windows	4-5
4.4.3	Configuring a Developer Kit to Run from a Shared Location (Windows)	4-6
4.5	Setting Up the GOCAD_LICENSE Environment Variable	4-7

Supported Operating Systems and Requirements

In this chapter

- "Common System Requirements," page 1-2
- "Additional Software Requirements," page 1-3
- "Specific Requirements for Supported Operating Systems," page 1-2
- "About Windows for x86 (32-Bit) and x64 (64-Bit) Systems," page 1-4

Overview

GOCAD 2009.1 and Basic Developer Kit 2009.1 require specific hardware and software to operate properly. The following topics describe the requirements for each supported operating environment, specific requirements for each operating system, and additional software requirements.

1.1 Common System Requirements

The following are minimum requirements and recommendations for all operating environments.

Memory	4 GB or more recommended ¹
hard disk space for GOCAD 2009.1	700 MB ²
Additional hard disk space for developer kits	200 MB ³
Pointing device	Three-button pointing device such as a mouse or trackball

1. The memory requirements listed are for normal usage of GOCAD 2009.1. Large data sets can require additional memory.
2. Disk space should be increased if extensions from other vendors are installed or if data is installed on local hard drives. To optimize performance, we recommend that you work on data locally.
3. The 200 MB requirement for installation of developer kits is in addition to the hard disk space requirement for GOCAD 2009.1.

1.2 Specific Requirements for Supported Operating Systems

This section lists supported operating systems for each environment and the environment-specific hardware requirements. For the most up-to-date system requirements, see the System Requirements page at <http://gocad-download.pdgm.com/sysreqs.php>.

Microsoft Windows for x86 systems (32 bits)¹

Operating system	Windows Vista (Business, Enterprise, or Ultimate Edition) and Windows XP Professional (Service Pack 2)
Hardware	<p>Processor. Intel® Core, Core 2 Duo, Core 2 Quad, or Xeon class processor; or AMD Athlon, Opteron, or Phenom class processor recommended.</p> <p>Graphics adapter. 3D graphics adapter with a minimum resolution of 1280x1204 pixels supporting OpenGL. NVIDIA Quadro series recommended.</p>
Software	<p>Development environment. (For developer kits only) Qt development license, Microsoft Visual Studio 2005 Professional Edition Service Pack 1 and ActiveState ActivePerl 5.10. You can find ActivePerl at: http://www.activestate.com/.</p>

1. You can run the x86 version of GOCAD 2009.1 on Windows x64 systems.

Microsoft Windows for x64 systems (64 bits)

Operating system	Windows Vista x64 (Business, Enterprise, or Ultimate Edition) and Windows XP Professional x64 Edition (for more information, see " About Windows for x86 (32-Bit) and x64 (64-Bit) Systems " on page 1-4).
Hardware	Processor. Intel Core, Core 2 Duo, Core 2 Quad, or Xeon class processor; or AMD Athlon, Opteron, or Phenom class processor recommended. Graphics adapter. 3D graphics adapter with a minimum resolution of 1280x1204 pixels supporting OpenGL. NVIDIA Quadro series recommended.
Software	Development environment. (For developer kits only) Qt development license, Microsoft Visual Studio 2005 Professional Edition Service Pack 1 and ActiveState ActivePerl 5.10. You can find ActivePerl at: http://www.activestate.com/ .

Linux for x64 systems (64 bits)

Operating system	Red Hat Enterprise Linux 4 and 5.
Hardware	Processor. Intel Core, Core 2 Duo, Core 2 Quad, or Xeon class processor; or AMD Athlon, Opteron, or Phenom class processor recommended. Graphics adapter. 3D graphics adapter with a minimum resolution of 1280x1204 pixels supporting OpenGL. NVIDIA Quadro series recommended.
Software	Video Driver. We recommend that you update to the latest NVIDIA driver. To download NVIDIA drivers, see http://www.nvidia.com/Download/index.aspx?lang=en-us . Development environment. (For developer kits only) <ul style="list-style-type: none">• For Red Hat Enterprise Linux: GCC 3.4.3 compiler.• For Red Hat Enterprise Linux 5: GCC 4.1.2 compiler.• Qt development license.

1.3 Additional Software Requirements

Web browser

Windows environments. Accessing Help on Windows requires one of the following browsers with JavaScript enabled: Microsoft Internet Explorer 6.0 or later.

Linux environments. Accessing Help on Linux requires a browser that supports Java and JavaScript.

Workaround for Firefox 3 users

If you use Firefox 3.0.x to access the Help, the hypertext links within the Help system do not work because Firefox version 3.0 has higher security settings than previous versions.

To work around this problem, follow these steps:

- 1 Open Firefox.
- 2 To access the advanced settings panel, in the address bar, type **about:config**.
- 3 When Firefox prompts you whether to proceed, click the **"I'll be careful, I promise"** button.
- 4 In the list of settings, change **security.fileuri.strict_origin_policy** to **false**.

Note This action disables a default security setting. If you are unsure whether this action is appropriate in your organization, consult your Information Technology department before proceeding.

Qt enterprise license (developer kits only)

Developers may need to purchase a Qt Enterprise License. For more information, see ["About Qt" on page 4-4](#).

1.4 About Windows for x86 (32-Bit) and x64 (64-Bit) Systems

GOCAD 2009.1 is available in a package that support Windows x64 (64-bit) systems. This package is designed for Windows Vista x64 Windows XP Professional x64 Edition, which are versions of Windows that run on processors of the x64 family made by Intel or Advanced Micro Devices (AMD).

You can use any 32-bit (x86) projects in the 64-bit (x64) version, but because x64 projects require more memory, not every 64-bit project will load in the 32-bit version.

You can install the 32-bit and 64-bit versions on the same x64 system. The versions are separated and do not interfere with each other.

Installing GOCAD 2009.1

In this chapter

- "Installation Process," page 2-2
- "Installing GOCAD 2009.1 and SKUA 2009.1," page 2-4
- "Downloading GOCAD, SKUA, and Related Products," page 2-2
- "Starting GOCAD 2009.1 or SKUA 2009.1," page 2-9

Overview

These topics explain how to install and start GOCAD 2009.1 in Linux and Windows environments.

2.1 Installation Process

Table 2–1 summarizes the installation process and lists where you can find information about how to complete each step.

Table 2–1 GOCAD 2009.1 installation process

Installation step	For information about this step, see this topic
1 Download the GOCAD 2009.1 software.	"Downloading GOCAD, SKUA, and Related Products" on page 2-2.
2 Install GOCAD 2009.1 on the client computer.	"Installing GOCAD 2009.1 and SKUA 2009.1" on page 2-4.
3 Install License Server 11.6 on the server for which the license file was issued.	Chapter 3, "Installing and Configuring License Server 11.6."
4 Start GOCAD 2009.1.	"Starting GOCAD 2009.1 or SKUA 2009.1" on page 2-9.

2.2 Downloading GOCAD and Related Products

You can download GOCAD and related products from:

<http://gocad-download.pdgm.com/>

All modules in the suite are packaged together.

The License Server program must be downloaded separately and installed on the computer that will serve licenses. For information about installation, see [Chapter 3, "Installing and Configuring License Server 11.6."](#)

If you purchased a developer kit, you also need to download this separately. For information about installation, see [Chapter 4, "Installing Developer Kits."](#)

Note Paradigm products are also available on DVDs (by request). The DVDs also include License Server. If you have the DVDs, you do not need to download the products from the Web site. For more information, see ["To request GOCAD and SKUA on DVD" on page 2-3.](#)

For more information, see:

- ["About the GOCAD 2009.1 and SKUA 2009.1 packages," page 2-3](#)
- ["To download GOCAD, SKUA, and related products," page 2-3](#)
- ["To request GOCAD and SKUA on DVD," page 2-3](#)

About the GOCAD 2009.1 packages

Table 2–2 lists the GOCAD 2009.1 packages. Multiple packages are available for the same customer to provide both 32-bit and 64-bit versions of the software.

Table 2–2 GOCAD 2009.1 packages

Operating system description	GOCAD 2009.1 packages to install
Windows Vista or Windows XP (32 bits) - x86	GOCAD-2009.1-Windows-i86.msi
Windows Vista or Windows XP (64 bits) - x64	GOCAD-2009.1-Windows-x64.msi
Red Hat Enterprise Linux 4 (64 bits) - x64	GOCAD-2009.1-Linux-amd64-re4.tar.gz
Red Hat Enterprise Linux 5 (64 bits) - x64	GOCAD-2009.1-Linux-amd64-re5.tar.gz

Note You can run the x86 Windows (32-bit) programs on x64 Windows (64-bit) systems.

To download GOCAD and related products

Downloading GOCAD and related products from the download site requires a logon name and password. This logon name and password are sent by e-mail along with the license file when you purchase a product. If you did not receive a logon name and password, contact Paradigm Customer Support at pdgm.com/support.

For each product that you want to download, do the following:

- 1 From the download page, <http://gocad-download.pdgm.com/2009.1>, navigate to the product page for the specific product that you want to download.
- 2 Click the **Download** link that applies to your operating system.

Note Linux files are TAR archives (.tar files) compressed with gzip. Windows files are either a Microsoft installer (.msi file) or an executable (.exe file).

- 3 When the dialog box opens, type the supplied logon name in the **User name** box and the password in the **Password** box, and then click **OK**.

Note The user name and password entries are case-sensitive. If you did not receive a user name and password or if they do not work, contact Paradigm Customer Support at pdgm.com/support.

- 4 When you are prompted to save or open the file, save the file to your hard disk drive or a networked server.

To request GOCAD on DVD

If you want a DVD of the GOCAD 2009 software, contact Paradigm Customer Support at pdgm.com/support.

Packages on DVDs are categorized by operating system. For information about the naming convention, see "About the GOCAD 2009.1 and SKUA 2009.1 packages" on page 2-3.

2.3 Installing GOCAD 2009.1

Separate instructions are included for Linux and Windows environments. Complete the procedure that corresponds to your environment.

If you have not yet downloaded GOCAD and you do not have the software on DVD, complete the procedure in "[Downloading GOCAD, SKUA, and Related Products](#)" on [page 2-2](#) before you continue.

2.3.1 Installing GOCAD on Linux

All GOCAD 2009.1 packages for Linux are installed by extracting a compressed archive into the main installation directory. All Paradigm products must reside under a common directory. The predefined directory name is PDGM.

If you plan to use GOCAD on multiple Linux operating systems, you need to download and install the package for each operating system. Multiple installations can reside in the same directory; the installation process handles correct file placement automatically.

Caution Do not move the PDGM directory contents. The subdirectories are specifically created by the installation process and must not change. You can rename the PDGM directory, but do not move or rename the subdirectories (for example, by using the **mv** command). Splitting the directories causes failures when GOCAD starts.

The following topics provide information about how to install GOCAD 2009.1 on Linux, configure GOCAD to run in a Paradigm™ Epos™ 4.0 environment, and configure OpenSpirit Client, an optional module. If you do not have a license for OpenSpirit Client or Epos, you can skip the related installation information.

To install GOCAD on Linux

- 1 Do one of the following:
 - If you downloaded the software and the file is not in the directory where you want to install the program, copy the file to the installation directory.
 - If you are installing the software from DVD, copy the package from the appropriate DVD to the installation directory.

- 2 To change to the installation directory, type the following command, where *installation_path_name* is a placeholder for the actual path name:

```
cd installation_path_name
```

- 3 Type the following command to extract the files:

```
gunzip < GOCAD-2009.1-platform.tar.gz | tar xvf -
```

Where *2009.1* is the version (for other versions, substitute your version designation) and *platform* matches the operating system and processor from the package name.

Important

- You cannot start GOCAD 2009.1 until License Server 11.6 and the license file are correctly installed on the server computer for which the license file was issued. For more information, see [Chapter 3, "Installing and Configuring License Server 11.6."](#)
- If you have a license for Reservoir Simulation Interface and you want to launch flow simulations from GOCAD, you need to create a run configuration file. For information, see the *Reservoir Simulation Interface Configuration Guide*.

- If you have a license for High-Performance Reservoir Risk Assessment (Jacta Cluster) and you want to run Jacta simulations on a cluster network, you need to install and configure a batch management system. For information, see the *High-Performance Reservoir Risk Assessment (Jacta Cluster) Configuration Guide*.

Note When installing a Linux archive on a Solaris file server, the extraction may fail because of differences between Solaris and Linux archives formats. In that case, you will need to apply patch 110951-01 on the **tar** extraction utility. You can verify the size of the archives by checking them on the Paradigm download Web page at <http://gocad-download.pdgm.com/2009>.

Installing the package creates the PDGM directory. The main executable is in: `/opt/PDGM/GOCAD-SKUA-2009.1/bin`.

Where *GOCAD-SKUA-2009.1* is the version designation. For other versions, substitute your version designation in the path name.

To configure OpenSpirit Client on Linux

If you have an OpenSpirit Client license, you must specify where OpenSpirit (the third-party program licensed by OpenSpirit Corporation) is installed on your computer; otherwise, OpenSpirit Client cannot connect to it. Although there is more than one method for specifying the location of OpenSpirit, we recommend that you save the `OSP_HOME` environment variable in your user profile as explained in the following procedure. If you installed an earlier version of GOCAD and you already completed this procedure, you do not need to do it again.

On Windows, the OpenSpirit Windows installer sets the `OSP_HOME` environment variable on the computer automatically, so no additional configuration is necessary. The following procedure applies to Linux operating systems only.

◆ Assuming OpenSpirit (the client program licensed by OpenSpirit Corporation) is installed in the `/appl/openspirit` directory, edit your Linux user profile to set the environment variable `OSP_HOME` according to your shell type as follows:

- If you are using the C shell, type:
setenv OSP_HOME /appl/openspirit
- If you are using the Korn or Bourne shell, type:

export OSP_HOME=/appl/openspirit

If OpenSpirit is installed in a different location, substitute the correct path.

Note If you want to use a different OpenSpirit installation temporarily, you can set the `OSP_HOME` variable in the shell that you are starting GOCAD from. Assuming OpenSpirit is installed in `appl/openspirit/openspirit-x.x.x`, for example:

- If you are using the C shell:
setenv OSP_HOME /appl/openspirit/openspirit-x.x.x
- If you are using the Korn or Bourne shell:
export OSP_HOME=/appl/openspirit/openspirit-x.x.x

To configure GOCAD to run in an Epos environment

If you have Epos installed and you have an Epos Link license, you can configure GOCAD to run as an Epos application, available from the Paradigm Session Manager.

- 1 After you install GOCAD, as the Epos administrator run the script **PG_emos_config**, located in the following directory: *Epos4 root directory*/Epos4/bin/.
- 2 Select the Runtime Variables and set **GOCADLMD_LICENSE_FILE** to the location of the license file used by GOCAD.

Note For more information about licensing, see "About Configuring Licenses for GOCAD 2009.1 and SKUA 2009.1," page 3-3.

- 3 Set the **PG_GOCAD_PATH** to the directory location where GOCAD has been installed.

For more information about installing and configuring Epos applications, see the *Rock & Fluid Canvas™ 2009 / Epos™ Installation Guide*.

2.3.2 Installing GOCAD on Windows

Complete the following procedure to install GOCAD on Windows.

To install GOCAD on Windows

- 1 If you downloaded the software, double-click the downloaded file.

– or –

If you are installing GOCAD from DVD, do the following:

- a Place the DVD for the Windows version of the software in your DVD drive, open **My Computer**, and double-click the DVD name to display the DVD contents.
- b Locate the folder on the DVD that contains one of the following files, choosing the appropriate one for your operating system, and then double-click the file:
 - For Windows Vista or Windows XP for x86 systems (32 bits), double-click **GOCAD-2009.1-Windows-i86.msi**.
 - For Windows Vista or Windows XP for x64 systems (64 bits), double-click **GOCAD-2009.1-Windows-x64.msi**.

Where *2009.1* is the version number. For other versions, substitute your version designation.

Whether you are using a DVD or a downloaded file, the installation wizard opens after a few moments.

- 2 Follow the on-screen instructions in the installation wizard.

Important

- We recommend that you have Administrator rights enabled when you install GOCAD. You can either log on as an account with Administrator rights, or you can right-click the GOCAD installation file (.msi), point to **Run As** on the shortcut menu, click **the following user** option, enter the user name, type the corresponding password, and then click **OK**.
- When GOCAD is installed on a server, it will not run on a local computer unless the runtime library Microsoft Visual C++ 2005 SP1 Redistributable Package that corresponds to the processor architecture of the GOCAD installation (x86 or x64) is installed on that computer. If you encounter a configuration error or a prompt to reinstall the application, complete the procedure in "[Configuring GOCAD and SKUA to Run from a Shared Location \(Windows\)](#)" on page 2-7.
- You cannot start GOCAD until License Server 11.6 and the license file are correctly installed on the server computer for which the license file was issued. For more information, see [Chapter 3, "Installing and Configuring License Server 11.6."](#)
- If you have a license for Reservoir Simulation Interface and you want to launch flow simulations from GOCAD, you must create a run configuration file. For information, see the *Reservoir Simulation Interface Configuration Guide*.

2.3.3 Configuring GOCAD to Run from a Shared Location (Windows)

If you are installing GOCAD (or a related developer kit) on a server in a Windows environment, you must ensure that Microsoft Visual C++ 2005 Redistributable Package is installed on each local computer from which the program will be run.

If you do not have Microsoft Visual C++ 2005 Redistributable Package installed, perform the following steps.

Notes

- To perform this procedure, you must have Administrator rights.
- You do not need to perform this procedure if you are installing GOCAD (or a related developer kit) to run on a local computer. For local installations, the installation program automatically installs the runtime library for your environment.

To configure GOCAD to run from a shared location (Windows only)

1 (This example assumes that the local client computer can access GOCAD through a UNC path to \\FileServer\Application corresponding to the GOCAD installation.) On the local client where GOCAD will be run, navigate to \\FileServer\Application\PDGM\GOCAD-SKUA-2009.1\Redist, where *GOCAD-SKUA-2009.1* is the version designation (for other versions, substitute your version designation), and then do one of the following:

- For Windows x86 systems (32 bit), locate and double-click the file **vcredist_x86.exe** to run it.
- For Windows x64 systems (64 bit), locate and double-click the file **vcredist_x64.exe** to run it.

Note For a network installation, navigate to this folder in the installation on the network or obtain the file from Microsoft:

- **x86 (32 bit).** <http://www.microsoft.com/downloads/details.aspx?FamilyID=200b2fd9-ae1a-4a14-984d-389c36f85647&DisplayLang=en>.
- **x64 (64 bit).** <http://www.microsoft.com/downloads/details.aspx?FamilyID=90548130-4468-4bbc-9673-d6acabd5d13b&DisplayLang=en>.

2 If you receive a message directing you to restart your computer, restart your computer to complete the installation.

2.4 Starting GOCAD 2009.1

Complete the procedure that corresponds to your operating system.

2.4.1 Starting GOCAD 2009.1 on Linux

You cannot start GOCAD until License Server 11.6 and the license file are correctly installed on the server computer for which the license file was issued. For more information, see [Chapter 3, "Installing and Configuring License Server 11.6."](#)

After GOCAD is installed, License Server is set up, and the license is configured, you can start GOCAD and connect to License Server.

To start GOCAD or GOCAD Viewer on Linux

- 1 If you installed GOCAD in the /opt directory, type the following command at a command prompt:

```
/opt/PDGM/GOCAD-SKUA-2009.1/bin/Gocad
```

– or –

If you want to start only the GOCAD Viewer, type the following command at a command prompt:

```
/opt/PDGM/GOCAD-SKUA-2009.1/bin/Gocad-Viewer
```

Where *GOCAD-SKUA-2009.1* is the version designation. For other versions, substitute your version designation.

Note If you installed GOCAD in a different location, substitute the correct path.

[Table 2–3 on page 2-10](#) lists common options that you can add to the command.

The **Open Existing or New Project** dialog box opens.

Note If GOCAD cannot connect to License Server, you will receive an error message. To configure License Server, set the GOCADLMD_LICENSE_FILE environment variable to *port@host*, where *port* is the TCP/IP number (typically 27000) and *host* is the name (or IP address) of the computer on which License Server is installed. (If you did not change the default port value for License Server, you can omit it.) If you do not know these values, contact your license administrator. Examples are @192.68.1.1 or 23456@license-server.

Tip For more information about starting the program, creating a project, and opening existing projects, see the *User Guide, Part I: Getting Started*.

- 2 Click **New Project**, find and open a folder, type a name in the **File name** box, and then click **Save** to open the **Project Module Selector**.

- 3 Do one of the following:

- To select all available modules, click **Select All**, and then click **OK**.
- To select modules individually, click each tab and select the check box next to each module that you want to load, and then click **OK**.

A splash screen appears as the program loads the selected modules. The program opens and prompts you to choose project units.

- 4 In the **Initialize Project Units** dialog box, select from the options and then click **OK**. For more information about project units, see the *User Guide, Part I: Getting Started*.

Table 2–3 Startup options

Option	Description
-help	Lists all the options that you can use when starting GOCAD.
-all-plugins	Loads all of the modules for which a license is available ¹ . If you use this option, the Project Modules Selector does not appear during startup.
-user-level Advanced	Presets the user level to Advanced when you start the program. You may find this option useful, for example, if you create a script or a shortcut to set the initial user preferences for many users. For information about the Advanced user level, see the <i>User Guide, Part I: Getting Started</i> .

1. If you have both GOCAD and SKUA modules, only those modules that are compatible with GOCAD will load in GOCAD, and only SKUA-compatible modules will load in SKUA.

Note The **-plug-in** option is no longer the recommended method to start custom modules. We recommend that plugin developers provide a custom package file. For information about package files, see the developer documentation provided with the developer kit that is located at the following path: *InstallationPath*\PDGM\GOCAD-SKUA-2009.1\doc\devkit-doc\Gocad-devkit.chm file. The package information is located in the Overviews section under Plugin Manager.

2.4.2 Starting GOCAD on Windows

You cannot start GOCAD until License Server 11.6 and the license file are correctly installed on the server computer for which the license file was issued. For more information, see [Chapter 3, "Installing and Configuring License Server 11.6."](#)

After GOCAD is installed, License Server is set up, and the license is configured, you can start GOCAD and connect to License Server.

For information about startup options that you can use when you start GOCAD, see [Table 2–3 on page 2-10](#).

To start GOCAD on Windows x86 Systems (32 bits)

- 1 On the Windows taskbar, click the **Start** button, point to **All Programs**, point to **Paradigm GOCAD 2009.1**, and then click **Paradigm GOCAD 2009.1**. (For other product versions, the shortcut location might be different.)
- 2 If you are starting GOCAD for the first time and the **FLEXnet License Finder** dialog box opens, do the following:
 - a Select **Specify the License Server**, and then click **Next**.
 - b Type a *port@host* value where *port* is the TCP/IP number (typically 27000) and *host* is the name (or IP address) of the computer on which License Server is installed. If you do not know these values, contact your license administrator.
 - c Click **OK**.

After you connect to License Server, the **Open Existing or New Project** dialog box opens.

- 3 Click **New Project**, find and open a folder, type a name in the **File name** box, and then click **Save** to open the **Project Module Selector**.
- 4 Do one of the following:
 - To select all available modules, click **Select All**, and then click **OK**.
 - To select modules individually, click each tab and select the check box next to each product that you want to load, and then click **OK**.

Tip For more information about starting the program, creating a project, and opening existing projects, see the *User Guide, Part I: Getting Started*.

A splash screen appears as the program loads the selected modules. The program opens and prompts you to choose project units.

- 5 In the **Initialize Project Units** dialog box, select from the options, and then click **OK**. For more information about project units, see the *User Guide, Part I: Getting Started*.

To start GOCAD on Windows x64 Systems (64 bits)

Important There is a known problem with the FLEXnet License Finder on all Windows x64 versions. The tool does not accept any license server information and always reports, "The License Server returned a networking error. See your System Administrator for assistance." The issue has been reported to Macrovision, but a corrected version of FLEXnet is not yet available. Complete the following procedure to work around the issue.

- 1 Set the environment variable on the client computer that is running GOCAD:
 - a Click the **Start** button, click **Settings** (if you are using the Classic Start menu), and then click **Control Panel**.
 - b In Control Panel, double-click **System** to open the **System Properties** window (Windows XP) or the **Advanced System Settings** window (Windows Vista).
 - c In either window, click the **Advanced** tab, and then click **Environment Variables** to open the **Environment Variables** panel.
 - d Under the **User variables** category, click **New** to open the **New User Variable** dialog box.
 - e In the **Variable name** box, type **GOCADLMD_LICENSE_FILE**; in the **Variable value** box, type the information to access License Server; and then click **OK**.

For the value in the **Variable value** box, use the format *port@host*, where *port* is the TCP/IP number (typically 27000) and *host* is the name (or IP address) of the computer on which License Server is installed. (If you did not change the default port value for License Server, you can omit it.) If you do not know these values, contact your license administrator.
 - f In the **Environment Variables** panel, check that GOCADLMD_LICENSE_FILE is defined as, for example, @192.68.1.1 or 23456@license-server, and then click **OK**.
 - g In the **System Properties** panel, click **OK**.

The program starts immediately, without displaying the FLEXnet License Finder, and the **Open Existing or New Project** dialog box opens.

Tip For more information about starting the program, creating a project, and opening existing projects, see the *User Guide, Part I: Getting Started*.

- 2 Click **New Project**, find and open a folder, type a name in the **File name** box, and then click **Save** to open the **Project Module Selector**.
- 3 Do one of the following:
 - To select all available modules, click **Select All**, and then click **OK**.
 - To select modules individually, click each tab and select the check box next to each module you want to load, and then click **OK**.

A splash screen appears as the program loads the selected modules. The program opens and prompts you to choose project units.

- 4 In the **Initialize Project Units** dialog box, select from the options and then click **OK**. For more information about project units, see the *User Guide, Part I: Getting Started*.

Installing and Configuring License Server 11.6

In this chapter

- "About License Server," page 3-2
- "About Configuring Licenses for GOCAD 2009.1 and SKUA 2009.1," page 3-3
- "Installing or Upgrading License Server 11.6 on Linux," page 3-6
- "Installing or Upgrading License Server 11.6 on Windows," page 3-9
- "Setting Up the License Option File—Basic Developer Kit (Developer-Based)," page 3-16
- "Updating the License File," page 3-17
- "Frequently Asked Questions About License Server," page 3-18

Overview

Before you can start GOCAD 2009.1, you need to install and configure the license server program. The following describes how to do this for both Linux and Windows environments.

3.1 About License Server

A *license server* is a program that makes software licenses available to another program (a *client program*). GOCAD 2009.1 requires a license server based on FLEXnet from Acrezzo Software (<http://www.acresso.com>) to control program usage according to the licenses purchased. Because our license server is built with FLEXnet 11.6, we refer to our product as License Server 11.6.

Important GOCAD 2009.1 will only work with License Server 11.6 or later. If you are already using a license server released by Paradigm or another vendor, you must upgrade to this version.

License Server is distributed as a separate package and must be downloaded separately.

License Server is backward-compatible with earlier licenses: The latest version of the License Server can also provide licenses for earlier versions of Paradigm products.

3.2 About Configuring Licenses for GOCAD 2009.1

All Paradigm products are licensed. You must have a license for the products you have installed before you can use them.

These topics provide information for system administrators and users about licenses. For information about types of licenses and license file components, see "License Types" on page 3-3 and "License File Components" on page 3-4.

Note For more information on License Server administration tools, see the *FLEXnet Licensing End User Guide*. The user guide is available on the Macrovision Web site at: http://www.globes.com/support/generic/utilities/flexnet_licensing_end_user_guide.pdf.

3.2.1 License Concepts

GOCAD 2009.1 acts as a client program that connects to a license server program to gain authorization for accessing certain software features. GOCAD 2009.1 connects to the program License Server 11.6 for this purpose.

License Server 11.6 and GOCAD 2009.1 can be installed on the *same* computer. License Server must be installed on the computer for which the license file is issued. The name of this computer is listed on the SERVER line in the license file. For more information and an example, see "SERVER lines" on page 3-4.

3.2.2 License Types

Licenses for Paradigm products are server-based, which means a license server must be installed before you can run the program. The licenses can be permanent or temporary. They have a limited number of *tokens*, which are the number of available concurrent usages. Client computers connect to License Server to gain the right to run the licensed software.

There are two types of licenses:

- **Shared.** If you receive a shared license, License Server is installed on a computer connected to a network. GOCAD 2009.1 can run on the same computer or on another computer and use the network to connect to License Server. License Server must run on the computer for which the license was issued. This computer is listed on the SERVER line in the license file. For an example, see "SERVER lines" on page 3-4.
- **Host-locked.** If you receive a host-locked license, GOCAD 2009.1 and License Server can run on only one computer. The name of the computer for which the license is issued is listed on the SERVER line and in the INCREMENT paragraph in the license file. For more information and examples, see "License File Components" on page 3-4. Host-locked licenses are typically issued for running GOCAD 2009.1 on a notebook computer that is not connected to a network.

3.2.3 License File Components

License files are text files that include paragraphs and lines of text. Understanding license files is helpful when you troubleshoot problems or talk to Paradigm Customer Support (pdgm.com/support).

SERVER and VENDOR Lines

SERVER lines License Server must be installed on the computer listed on the SERVER line in the license file. The file includes only one SERVER line for a standard license server; whereas, the file includes three lines for triple redundancy servers. With triple redundancy, if one server fails, the two remaining servers take over and perform as the license server. The three servers store the same information and must be able to communicate through the network at any time.

SERVER lines are formatted as follows:

```
SERVER license-server 123456789012 27000
```

where:

license-server is the server name. (The license administrator can change this name.)

123456789012 is the server computer FLEXnet Host ID. (Do not change this number. Any change to it invalidates the license.)

27000 is the TCP/IP port number. (The license administrator can change this number.)

License Server listens to at least one TCP/IP port so that clients can connect to the license server on that port. By default, the TCP/IP port used by License Server is 27000.

If a third-party product license server is using the 27000 default port, you may change the port from 27000 to an unused one.

If you change the port, the new port number must be communicated to end users because it is needed when starting GOCAD 2009.1 for the first time. See "[Starting GOCAD 2009.1](#)" on page 2-8.

VENDOR lines The license file can include one VENDOR line for all server-based license files for Paradigm products. VENDOR lines are formatted as follows:

```
VENDOR gocadlmd
```

where: *gocadlmd* is the name of the license service program for Paradigm products.

INCREMENT Paragraphs

INCREMENT paragraphs define the characteristics of the license: its duration, the number of tokens, and so on. The license file includes an increment for each product or feature that you purchased.

Important Any change to the INCREMENT paragraphs invalidates the license.

INCREMENT paragraphs are formatted as follows:

```
INCREMENT gocad_base gocadlmd 200512.31 31-dec-2008 50 \
5BCF5BEB731B HOSTID=1234567890ab SUPERSEDE \
ISSUED=16-Aug-2007 ck=118 SN=... \
START=10-May-2007 SIGN=... \
SIGN2=...
```

where:

gocad_base	is the feature name corresponding to this increment.
200512.31	is the maintenance expiration date. This license allows users to run Paradigm products released before that date.
31-dec-2008	is the license expiration date. The date is "permanent" for permanent licenses.
50	is the number of tokens (available concurrent usages) in the license
HOSTID= 1234567890ab	Indicates that the INCREMENT package is locked on the server computer that has FLEXnet Host ID 1234567890ab. This line is present in all host-locked licenses.

3.3 Installing or Upgrading License Server 11.6 on Linux

The following sections describe how to either upgrade from an earlier version of License Server or perform a fresh installation in a Linux environment.

It is necessary to install License Server 11.6 on only the server computer for which the license file is issued. In larger organizations, License Server is installed on a server computer while GOCAD 2009.1 is installed on many client computers. With this scenario, if your computer is one of the client computers, you do not need to install License Server on it.

If you are upgrading an earlier version of License Server to the latest version, see ["Removing an Earlier Version of License Server" on page 3-6](#). If you are performing a new installation, complete the procedures in ["Installing a New License Server" on page 3-7](#).

3.3.1 Removing an Earlier Version of License Server

The following describes how to remove the version of License Server that controlled access to earlier versions of Paradigm products.

A license server may not be installed on your computer if you were using a license file that was installed on a remote server or if you were using a type of license, called a node-locked, serverless license, that did not require a license server.

To remove an earlier version of License Server

- 1 Shut down License Server by typing the following command in the installation directory for the server program:

```
cd InstallationPath/PDGM/Licenses  
./lmdown
```

Where *InstallationPath* is the path to the PDGM installation directory.

- 2 Ensure that the script that starts License Server at boot time is disabled.
- 3 Ensure that you keep a copy of your old license file. You can name it, for example, gocadlmd.bak.

Note Your current license file should have the path name *InstallationPath*/PDGM/Licenses/gocadlmd.lic.

- 4 If you have an option file for the Basic Developer Kit (Developer-Based) license, gather the list of user names that you want to authorize to access the license.

For information about the option file, see ["Setting Up the License Option File—Basic Developer Kit \(Developer-Based\)" on page 3-16](#).

- 5 Remove all of the files in the *InstallationPath*/PDGM/Licenses folder that were distributed with the previous version of the License Server. These files include Imgrd, gocadlmd, lmutil.

After you remove the earlier version of License Server, you can install License Server 11.6.

3.3.2 Installing a New License Server

Complete the following procedures to install a new License Server in a Linux environment.

To create a dedicated account for License Server

For security reasons, we recommend that you do not start License Server as *root*. We suggest that you create a dedicated account (for example, *paradigm*) with restricted rights on the server computer. Use this account each time you want to stop or restart License Server or install new licenses.

To download License Server files

- ◆ If you do not have GOCAD 2009.1 on DVD, download one of the License Server packages from the Paradigm download site: <http://gocad-download.pdgm.com/>. Download the package that corresponds to your operating system.

Note License Server packages for all supported operating systems are distributed on the DVDs.

To install License Server

- 1 Do one of the following:
 - If you downloaded License Server and the file is not in the directory where you want to install the program, copy the file to the installation directory.
 - If you are installing License Server from DVD, copy the package from a GOCAD 2009.1 DVD to the installation directory. (License Server packages for all supported operating systems are included on the DVDs.)
- 2 Type the following command to move to the installation directory:
cd *InstallationPath*
- 3 Type the following command to extract the License Server files, where *platform* matches the operating system and processor from the package name:
gunzip < LicenseServer-11.6.*platform*.tar.gz | tar xvf -
This creates a folder named PDGM/Licenses, which contains all License Server programs and utilities.

To install the license file

- ◆ Copy the license file that you received from Paradigm to the folder *InstallationPath*/PDGM/Licenses. Rename the license file *gocadlmd.lic*.

Important The SERVER line in the license file must reflect the name of the computer for which the license file is issued. If this is not the case, the SERVER line must be edited. For more information, see "SERVER lines" on page 3-4.

To set up the license option file—Basic Developer Kit (Developer-Based)

If you have a Basic Developer Kit (Developer-Based) license, you must also set up a license option file. For information, see "Setting Up the License Option File—Basic Developer Kit (Developer-Based)" on page 3-16.

To start License Server

- ◆ Do one of the following to start License Server:
 - If you are using the C shell, type a command similar to the following example:
cd *InstallationPath*/PDGM/Licenses
./lmgd -c gocadlmd.lic >& gocadlmd.log

- If you are using either the Korn or Bourne shell, type a command similar to the following example:

```
cd InstallationPath/PDGM/Licenses  
./lmgd -c gocadlmd.lic > gocadlmd.log 2>&1
```

Note lmgd is the License Server daemon.

License Server starts in the background and logs the server output to the file PDGM/Licenses/gocadlmd.log.

We recommend that you configure your computer to run the License Server automatically at system startup.

You can check the content of gocadlmd.log for any error messages. If there are error messages and you need assistance, contact Paradigm Customer Support at: pdgm.com/support.

Ensure that you include a copy of the gocadlmd.log file and your licence file in your support request.

Where to go from here

After you install License Server, you can start GOCAD 2009.1. For information, see "Starting GOCAD 2009.1 on Linux" on page 2-8.

3.3.3 Stopping License Server

The following explains how to stop License Server in a Linux environment.

To stop the License Server

- ◆ Type the following commands to stop the License Server:

```
cd InstallationPath/PDGM/Licenses  
./lmdown
```

3.4 Installing or Upgrading License Server 11.6 on Windows

The following sections describe how to either upgrade from an earlier version of License Server or perform a fresh installation in a Windows environment.

It is necessary to install License Server 11.6 on only the server computer for which the license file is issued. In larger organizations, License Server is installed on a server computer while GOCAD 2009.1 is installed on many client computers. With this scenario, if your computer is one of the client computers, you do not need to install License Server on it.

If you are upgrading an earlier version of License Server to the latest version, see ["Removing an Earlier Version of the License Server" on page 3-9](#). If you are performing a new installation, complete the process described in ["Installing a New License Server" on page 3-11](#).

3.4.1 Removing an Earlier Version of the License Server

This section presents instructions for removing the version of License Server that controlled access to earlier versions of Paradigm products.

A license server may not be installed on your computer if you were using a license file that was installed on a remote server or if you were using a type of license, called a node-locked, serverless license, that did not require a license server.

To deactivate the License Server

- 1 Ensure that you keep a copy of your old license file. You can name it, for example, `gocadlmd.bak` (in `InstallationPath\PDGM\Licenses`).
Note Your current license file should have the path name `InstallationPath\PDGM\Licenses\gocadlmd.lic`.
- 2 If you have an option file for the Basic Developer Kit (Developer-Based) license, gather the list of user names that you want to authorize to access the license.
For information about the option file, see ["Setting Up the License Option File—Basic Developer Kit \(Developer-Based\)" on page 3-16](#).
- 3 To start the License Server configuration tool, click **Start** on the Windows taskbar, point to **All Programs**, point to **Earth Decision License Manager > License Server Configuration Utility 11.3**. (For other versions, the shortcut is in a different location on the menu.)
– or –
Locate and run `lmttools.exe`.
- 4 On the **Service/License File** tab, select **Configuration Using Services**.
- 5 On the **Configure Services** tab, clear the **Start Server at Power Up** and **Use Services** check boxes.
- 6 Restart the computer.

To remove the License Server

- 1 On the Windows taskbar, click **Start**, click **Control Panel**, and then double-click **Add or Remove Programs**.
- 2 Select **FLEXnet License Server x.x** (the earlier version of FLEXnet), and then click **Remove**.
- 3 When you are prompted to confirm that you want to remove the FLEXnet License Server, click **Yes**.

After you remove the earlier version of the License Server, you are ready to install License Server 11.6.

3.4.2 Installing Dongle Device Drivers

Dongle licenses require that special drivers be installed on the computer to which the dongle is attached. Dongle licenses work only with Microsoft Windows operating systems. The type of dongle is determined by the FLEX ID, which is labeled on the dongle itself.

The dongle drivers can be downloaded from the Paradigm download site, and they are included on the GOCAD 2009.1 DVD for Windows environments. The drivers are set up by an automatic installation program.

To download the dongle device drivers (dongle license only)

- ◆ If you do not have GOCAD 2009.1 on DVD, download the Dongle Driver package from the download site at <http://gocad-download.pdgm.com/2009.1>.

To install Dongle Drivers (dongle license only)

- 1 If you downloaded the Dongle Driver package, double-click the downloaded file.
 - or –
 - If you are installing the Dongle Driver package from DVD, do the following:
 - a Place the GOCAD 2009.1 DVD for Windows in your DVD drive, open **My Computer**, and then double-click the DVD name to display its contents.
 - b Open the **DongleDrivers** folder, and then double-click **DongleDrivers-VersionNumber-Windows.exe**.
- 2 Follow the on-screen instructions in the installation wizard.

3.4.3 Installing a New License Server

Complete the following procedures to install the new License Server in a Windows environment:

- "To download License Server files," page 3-11
- "To install License Server," page 3-11
- "To install the license file," page 3-14
- "To set up the license option file—Basic Developer Kit (Developer-Based)," page 3-15
- "To finish License Server configuration," page 3-15
- "Where to go from here," page 3-15

Note You need Administrator rights to install License Server.

To download License Server files

- ◆ If you do not have GOCAD 2009.1 on DVD, download the License Server package for Windows from the Paradigm download site: <http://gocad-download.pdgm.com/2009.1>.

Note License Server packages for all supported operating systems are included on the DVDs.

To install License Server

- 1 If you downloaded License Server, double-click the downloaded file.
– or –
If you are installing License Server from DVD, do the following:
 - a Place a GOCAD 2009.1 DVD in your DVD drive, open **My Computer**, and double-click the DVD name to display its contents. (License Server packages for all supported operating systems are included on the DVDs.)
 - b Open the **LicenseServer** folder, and then double-click **LicenseServer-11.6-Windows.msi**.
The **InstallShield Wizard** opens.
- 2 Follow the on-screen instructions in the installation wizard.

To install the license file

- ◆ Copy the license file that you received from Paradigm (gocadlmd.lic) into the folder *InstallationPath*\PDGM\Licenses.

Important The SERVER line in the license file must reflect the name of the computer for which the license file is issued. If this is not the case, you need to edit the SERVER line. For more information, see "SERVER lines" on page 3-4.

To set up the license option file—Basic Developer Kit (Developer-Based)

If you have a Basic Developer Kit (Developer-Based) license, you must also set up a license option file. For information, see "Setting Up the License Option File—Basic Developer Kit (Developer-Based)" on page 3-16.

To finish License Server configuration

- 1 On the Windows taskbar, click **Start**, point to **All Programs**, point to **License Server**, and then click **License Server Configuration Utility**. A dialog box with several tabs opens.
- 2 On the **Service/License File** tab, click **Configure Using Services**, and then click **License Server** in the list.
- 3 On the **Config Services** tab, select the **Use Services** and **Start Server at Power Up** check boxes.
- 4 Click **Save Service**.
- 5 Restart the computer.

You can check the content of gocadlmd.log located in *InstallationPath*\PDGM\Licenses for any error messages. If there are error messages and you need assistance, contact Paradigm Customer Support at pdgm.com/support. Ensure that you include a copy of the gocadlmd.log file in your support request.

Where to go from here

After you install License Server, you can start GOCAD 2009. For more information, see "Starting GOCAD on Windows" on page 2-9.

3.5 Setting Up the License Option File—Basic Developer Kit (Developer-Based)

The Basic Developer Kit (Developer-Based) license requires that you specify the user names of the license users in an option file. The option file must be named `gocadlmd.opt`, and it must be in the same folder as `gocadlmd.lic`. This file can be modified at any time without affecting the validity of the license; however, License Server must be restarted if you modify the file.

To set up the license option file for Basic Developer Kit (Developer-Based)

- 1 Remove the # character from the GROUP line in the `gocadlmd.opt` file (included in the License Server package) and modify the list of logon names authorized to access the developer kit.

```
# GOCAD License Server Option File
#
# Uncomment the following GROUP line if you have purchased
# a "Basic Developer Kit (Developer-Based) "
# license.
# The following line should contain the list of
# logins authorized to access the license.
#
# GROUP Developers login1 login2 login3 ← GROUP line
#
.
.
.

#EOF
```

Note The number of users you specify cannot exceed the number of licenses granted in the license file. You can find this number in the INCREMENT paragraph (see ["INCREMENT Paragraphs" on page 3-5](#)) of the license file for the Basic Developer Kit (Developer-Based) product. If the number of users you specify is less than the number of licenses granted in the license file, the remaining licenses *will not* be available.

- 2 Restart License Server.

Important You must restart License Server any time you modify the option file. Reloading the server with the **Imreread** command is not sufficient.

3.6 Updating the License File

This section explains how to update the license file. Updating the license file is necessary if, for example, you purchase a new Paradigm product or renew your maintenance contract. In these cases, Paradigm sends you a new license file that fully replaces all previously issued license files. You cannot combine license files.

Complete the procedure for your environment. License Server 11.6 should be running before you start the following procedures.

To replace the license file on Linux

- 1 In the *InstallationPath*/PDGM/Licenses directory, replace the current license file (gocadlmd.lic) with the new license file, naming the new file **gocadlmd.lic**.

Note You can keep a copy of an old license file in the same folder by renaming it, for example, gocadlmd.bak.

- 2 Restart License Server. For information, see ["To start License Server" on page 3-7](#).

To replace the license file on Windows

- 1 In the *InstallationPath*/PDGM/Licenses folder, replace the current license file (gocadlmd.lic) with the new license file, naming the new file **gocadlmd.lic**.

Note You can keep a copy of an old license file in the same folder by renaming it, for example, gocadlmd.bak.

- 2 Restart the computer.

3.7 Frequently Asked Questions About License Server

This section answers the following frequently asked questions about License Server:

- "How Do I Find the Host ID for My Computer?," page 3-18
- "How Do I Switch from One License Server to Another?," page 3-19
- "What Is the GOCADLMD_LICENSE_FILE Environment Variable?," page 3-20

3.7.1 How Do I Find the Host ID for My Computer?

The Host ID is a 12-character (Microsoft Windows, Linux) hexadecimal number that provides the physical address of the Ethernet card. It is neither the workstation's IP address, nor the serial number.

To get the Host ID on Windows

Although there are other methods, use the following one to ensure the you find the required Host ID.

- 1 On the Windows taskbar, click **Start**, and then click **Run**.
- 2 Type **cmd**, and then click **OK** to open a command prompt.
- 3 Type **ipconfig /all**, and then press ENTER to see information such as the following:

```
Windows IP Configuration

    Host Name . . . . . : mycomputer
    Primary Dns Suffix . . . . . : mycompany.com
    Node Type . . . . . : Unknown
    IP Routing Enabled. . . . . : No
    WINS Proxy Enabled. . . . . : No
    DNS Suffix Search List. . . . . : mycompany.com

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix . . : mycompany.com
    Description . . . . . : Broadcom 440x 10/100
    Integrated Controller
    Physical Address. . . . . : 00-0D-56-AF-18-0F
    Dhcp Enabled. . . . . : Yes
    Autoconfiguration Enabled . . . . . : Yes
    IP Address. . . . . : 10.1.13.32
    Subnet Mask . . . . . : 255.255.0.0
    Default Gateway . . . . . : 10.1.1.1
    DHCP Server . . . . . : 10.1.10.57
    DNS Servers . . . . . : 10.1.10.57
    . . . . . : 10.1.10.24
    Lease Obtained. . . . . : June 05, 2008
    Lease Expires . . . . . : June 18, 2008
```

- 4 Send the all of the resulting output to the person who requested the Host ID.

Important Be sure to send the full contents of ipconfig/all, especially if your computer is a notebook. To generate a license, Paradigm requires the physical address: the Host ID of the fixed Ethernet card, not the wireless one.

To get the Host ID on Linux

Retrieve the Host ID by using the `lmhostid` utility, which you can download from the Paradigm download site. Running `lmhostid` within Linux gives you a 12-character Host ID. Although there are several Linux "hostid" commands, they return a number that does not correspond to the required Host ID. Only the following method is accurate.

- 1 Download `lmhostid` for your operating system from the Paradigm download site at <http://gocad-download.pdgm.com/2009.1>.
- 2 Type the following command at a command prompt to set execution rights on the `lmhostid` utility, where *platform* matches the operating system and processor from the package name:

```
chmod u+x ./lmhostid-11.6-platform
```

Type the following command at a command prompt to rename the `lmhostid` utility:

```
mv ./lmhostid-11.6-platform lmhostid
```

- 3 Type the following command at a command prompt to run the `lmhostid` utility:
./lmhostid

Running `lmhostid` gives you results similar to the following:

```
% lmhostid
lmhostid -Copyright (C) 1989-2002 Globetrotter Software, Inc.
The FLEXnet host ID of this machine is "12345678"
```

- 4 Send the resulting output to the person who requested the Host ID.

3.7.2 How Do I Switch from One License Server to Another?

The information for the license server you are using is stored in the registry on Windows and in `$HOME/.flexlmrc` on Linux. On Windows, to switch from one License Server to another, you need to delete this information from the registry. On Linux, you need to remove the file `$HOME/.flexlmrc`. You might want to do this, for example, to switch from the License Server on your computer to one on a network.

To switch from one License Server to another on Windows

- 1 Click the **Start** button, click **Run**, type **regedit**, and then click **OK**.
- 2 In the **Registry Editor**, click the **Edit** menu, and then click **Find**.
- 3 In the **Find** dialog box, type **GOCADLMD_LICENSE_FILE**, and then click **Find Next**.
- 4 When the list of files appears, delete **GOCADLMD_LICENSE_FILE**.

When you start GOCAD 2009.1, the **FLEXnet License Finder** dialog box opens and you are prompted to specify the license server. For information about how to specify the license server, see "[Starting GOCAD on Windows](#)" on page 2-9.

To switch from one License Server to another on Linux

- ◆ Type the following command at a command prompt, and then press ENTER:

```
rm $HOME/.flexlmrc
```

You can now start GOCAD 2009.1. For information, see "[Starting GOCAD 2009.1 on Linux](#)" on page 2-8.

3.7.3 What Is the GOCADLMD_LICENSE_FILE Environment Variable?

GOCADLMD_LICENSE_FILE is an environment variable that can specify explicitly where GOCAD 2009.1 searches for license information. The value of this variable is *port@host*, where *port* is the TCP/IP number and *host* is a server name such as *server.mycompany.com* or an IP address such as 192.168.1.1.

If you are installing License Server locally on a Windows 64-bit computer or you are running GOCAD 2009.1 on a Windows 64-bit computer and connecting to a remote License Server, you must set this environment variable. For information, see "[To start GOCAD on Windows x64 Systems \(64 bits\)](#)" on page 2-10.

You can also use this environment variable for troubleshooting your License Server. To switch from one license server to another, see "[How Do I Switch from One License Server to Another?](#)" on page 3-19.

Otherwise, setting this environment variable is not required to run GOCAD 2009.1, and we recommended that you do not use it.

Installing Developer Kits

In this chapter

- "About Developer Products," page 4-2
- "Installation Process," page 4-2
- "About Qt," page 4-4
- "Installing Developer Kits," page 4-4
- "Setting Up the GOCAD_LICENSE Environment Variable," page 4-7

Overview

The Basic Developer Kit 2009.1 and the Workflow Developer Kit 2009.1 are products that developers can use to build software based on Paradigm technology. To use a developer kit, you need to install and configure the software in a Windows or Linux environment.

4.1 About Developer Products

Paradigm offers three developer products:

- **Basic Developer Kit (Shared).** This product incorporates a subset of GOCAD Base Module functionality for use in development. Basic Developer Kit requires that you first install GOCAD 2009.1. The Basic Developer Kit license permits use of the product only for the purposes of developing and testing independent programs or GOCAD plug-ins. This license also permits sharing the Basic Developer Kit among developers in an organization.
- **Basic Developer Kit (Developer-Based).** This product is identical to Basic Developer Kit (Shared) except that this license does not permit sharing among developers in an organization. The license provides access only for a specific developer.

These products are packaged together, so you do not need to download multiple packages.

- **Workflow Developer Kit.** This product includes workflow functionality that builds on the functionality of the Basic Developer Kit. It requires that you first install GOCAD 2009.1 and the Basic Developer Kit.

4.2 Installation Process

If you have not done so already, install GOCAD 2009.1 on the computer where you intend to install the developer kit. For information, see ["Installing GOCAD 2009.1" on page 2-4](#).

[Table 4–1](#) summarizes the developer kit installation process and lists where you can find information about how to complete each step.

Table 4–1 Installing a developer kit

Installation step	For information about the step, see
1 Purchase a Qt Enterprise License if required for your environment.	"About Qt," page 4-4
2 Download the Basic Developer Kit software.	"Downloading GOCAD and Related Products," page 2-2
3 (Optional) Download the Workflow Developer Kit 2009.1.	"Downloading GOCAD and Related Products," page 2-2
4 Install Basic Developer Kit on the computer where you installed GOCAD 2009.1.	"Installing Developer Kits," page 4-4
5 For each developer who will use Basic Developer Kit (Shared or Developer-Based), set up the GOCAD_LICENSE environment variable.	"Setting Up the GOCAD_LICENSE Environment Variable," page 4-7

Installation step	For information about the step, see
<p>6 For each developer who will use Basic Developer Kit (Developer-Based), set up the license server option file to contain the developer's user name.</p>	<p>"Setting Up the License Option File—Basic Developer Kit (Developer-Based)," page 3-16</p>
<p>7 (Optional) Install the Workflow Developer Kit.</p>	<p>The Workflow Developer Kit installation process is similar to developer kit installation process as described in "Installing Developer Kits," page 4-4. It is installed in the same directory as the Basic Developer Kit.</p>

4.3 About Qt

Do I need to purchase a Qt Enterprise license?

For Linux, Basic Developer Kit contains Qt libraries and header files that will allow you to create modules and plug-ins. Most development on Linux does not require the purchase of a Qt Enterprise License. However, if your development uses the Qt utilities moc and uic, you will need to purchase a Qt Enterprise License from Trolltech.

For Windows, a Qt Enterprise License is required to develop with Basic Developer Kit.

To obtain and install Qt

If you determine that you need to purchase a Qt Enterprise License, complete the following procedure:

- 1 Purchase a Qt Enterprise License from the Trolltech Web site: <http://qtsoftware.com/contact>.
- 2 Submit the e-mail confirming that you purchased Qt Enterprise License from Trolltech to Paradigm Customer Support at pdgm.com/support.

Upon receipt, Paradigm will send you the logon name and password that you need to download the GOCAD Qt libraries.

- 3 Download the GOCAD Qt libraries. For information, see "[Downloading GOCAD and Related Products](#)" on page 2-2.
- 4 Extract the downloaded file into the PDGM installation folder.

4.4 Installing Developer Kits

The steps to install a developer kit are different for Linux and Windows environments. Complete the procedures for your environment.

Before you can install a developer kit, you need to obtain a developer kit package for your operating environment. If you have not downloaded a package or obtained a DVD, complete the steps in "[Downloading GOCAD and Related Products](#)" on page 2-2 before you continue.

You should also ensure that GOCAD 2009.1 is installed before you begin the following procedures to install a developer kit.

4.4.1 Installing a Developer Kit on Linux

All developer kit packages for Linux are installed in the main installation directory by extracting a compressed archive. All Paradigm products must reside under a common directory, such as the predefined directory name, PDGM.

If you plan to use a developer kit on multiple Linux operating systems, you need to download and install the developer kit package for each operating system. The installation process handles correct file placement automatically, allowing multiple installations to reside in the same directory.

Important You need to install Basic Developer Kit where you installed GOCAD 2009.1.

To install a developer kit on Linux

- 1 Do one of the following:
 - If you downloaded a developer kit package and the file is not in the directory where you want to install the program, copy the file to the installation directory.
 - If you obtained a developer kit package on DVD, copy the package from the appropriate DVD to the installation directory.
- 2 Type the following command to move to the installation directory:
cd *installation_directory*
- 3 Type the following command to extract the files:
gunzip < Basic-Developer-Kit-2009.1-*platform*.tar.gz | tar xvf -
Where 2009.1 is the version number (for other versions, substitute your version number) and *platform* matches the operating system and processor from the package name.

4.4.2 Installing a Developer Kit on Windows

Complete the following steps to install a developer kit on Windows.

Important You need to install Basic Developer Kit where you installed GOCAD 2009.1.

To install a developer kit on Windows

- 1 If you downloaded a developer kit package, locate and double-click the downloaded file.
– or –
If you obtained a developer kit package on DVD, do the following:
 - a Place the DVD in your DVD drive, open **My Computer**, and double-click the DVD name to display the DVD contents.
 - b Open the **Developer Kit** folder, and then double-click the following file:
Basic-Developer-Kit-2009.1-*platform*.msi
Where *2009.1* is the version number (for other versions, substitute your version designation) and *platform* matches the operating system and processor from the package name.
- Whether you are using a DVD or a downloaded file, the installation wizard opens after a few moments.

- 2 Follow the on-screen instructions in the installation wizard.

Notes

- If a developer kit is installed on a server, it will not run on a local computer unless the runtime library MSVCR80.dll is installed. If you attempt to run a developer kit locally and this library is not installed, a message notifies you that the program failed to start because MSVCR80.dll was not found. If you receive this message, complete the steps in "[Configuring GOCAD to Run from a Shared Location \(Windows\)](#)" on page 2-7.
- Although you can install the x64 version developer kit, you will only be able to develop products for the x86 environment.

4.4.3 Configuring a Developer Kit to Run from a Shared Location (Windows)

For Windows environments, if you installed a developer kit on a server, the necessary runtime library must be installed for the program to run on a local computer.

The process for installing the runtime library for a developer kit is the same as that for configuring GOCAD to run on a server. For information, see "[Configuring GOCAD to Run from a Shared Location \(Windows\)](#)" on page 2-7.

4.5 Setting Up the GOCAD_LICENSE Environment Variable

If you have a Basic Developer Kit license, you need to set the **GOCAD_LICENSE** environment variable to **dsl** for each developer who will use the product.

To set GOCAD_LICENSE environment variable on Linux

- ◆ Do one of the following:
 - If you are using C Shell, type the following at a command prompt:
setenv GOCAD_LICENSE dsl
 - If you are using Korn Shell, type the following at a command prompt:
export GOCAD_LICENSE=dsl

To set GOCAD_LICENSE environment variable on Windows

- 1 Right-click **My Computer**, and then select **Properties** to open the **System Properties** dialog box.
- 2 Click the **Advanced** tab, and then click **Environment Variables**.
- 3 In the **User Variables** section at the top, click **New** to open the **New User Variable** dialog box.
- 4 In the **Variable name** box, type **GOCAD_LICENSE**.
- 5 In the **Variable value** box, type **dsl**.
- 6 Click **OK**.

